

A decorative graphic consisting of a thin yellow circle on the left side. A horizontal bar, colored olive green on the left and fading to white on the right, passes through the circle. A large black left square bracket is positioned on the left side of the bar, and a large yellow right square bracket is on the right side.

Aquifer Water Quality

CAMP

Rathdrum Prairie Advisory
Committee, Meeting #2

January 29, 2010

[PHD Aquifer Protection Rules]

- Over 30 years protecting the aquifer
- IDAPA 41.01 Rules of PHD1
 - 1977 - Five Acre Rule
 - 1990 – Critical Materials Regulation
- Protection Program now funded by Kootenai County through the Aquifer Protection District

[Sewage Management]

- Dalton Gardens
- Farragut State Park
- Athol
- Coeur d'Alene
- Hayden Lake Recreational Water and Sewer District

[2009 Critical Materials Program]

- 17,800,000 gallons stored
 - Many times this amount handled yearly
- 828 businesses
 - Down from 950 in 2009: mostly data base cleaning
- 31 new business applications

[Boots on the Ground]




[Business Visits Conducted]

	<u>2007</u>	<u>2008</u>	<u>2009</u>
■ Total Visits	187	450	584

[Water Quality Monitoring]

- Same select 27 wells tested three times a year
- High quality water maintained

[Monitoring Well Locations]





Water Quality Timeline

Water Quality


The illustrations on this page show concentrations of nitrate in the Aquifer through time. Nitrate is composed of nitrogen and oxygen and is highly stable in the water in soil and aquifer sediments. Under natural conditions, nitrate occurs in very low concentrations, typically less than 0.1 part per million (ppm). Nitrate in drinking water above 10 ppm may cause illness. Septic systems, fertilizer, and stormwater are major causes of elevated nitrate levels in the Aquifer.

The earliest nitrate concentration map is from the water year October 1977 to September 1978, which represents earlier stages of Aquifer protection activities in Washington and Idaho. The peak of observed nitrate degradation in the entire Aquifer was in the water year 1984-85. In 1985 a major effort on both sides of the state line was initiated to reduce septic system contamination of the Aquifer through installation of piped sewer collection systems. On all the maps, certain areas near the edge of the Aquifer show high levels of nitrate. These locations represent "eddy" areas where incoming contaminants from side hill development are not easily or quickly mixed with better quality water recharging from the east.

As the maps indicate, ongoing Aquifer protection programs have decreased the nitrate contamination despite significant population increases. These programs include installation of sewers and stormwater management. The groundwater in the Aquifer remains some of the best quality water available anywhere.




Dalton Gardens




[East Greenacres]

Well # 112 East Greenacres




Mountain View Terrace, PF

Well # 113 Mtn. View Terrace



[Post Falls]

Well # 104 Post Falls #3 Idaho Rd





Questions?